


App User Guide

Use of the **W4A Key App** on Android and iOS devices.

Information

The interaction profiles with the device are defined according to their functions and organized under the following hierarchical levels:




The **Installer** profile is solely responsible for the **installation** and **configuration** of the device and must therefore be the first profile created. All remaining profiles are usage profiles derived from the **Installer** profile.

Before proceeding with configuration, ensure that the device is properly installed and powered on.


1. Installation and Configuration of the Device

- 1.1. Select **Install New Device** from the **Add** menu to create the **Installer** profile.
- 1.2. Select the desired device.

Note: To access the Add menu, tap the icon  and then press the button .







1.3. Creation of access credentials for the Installer profile (assignment of a Bluetooth name to the device and definition of the Installer profile passphrase).





Note: The defined passphrase will be required to access the device; therefore, it must be kept in a secure location..

1.4. After successful creation of the Installer profile, the App will display the device management menu, where the device can be viewed and configured. In the future, to access this menu, simply select the **Installer** menu and choose the desired device.

- 1.5. To view device information, navigate to the **Information** tab.
- 1.6. To configure the device behavior, navigate to the **Device** tab.



1.7. To define the desired actuations, navigate to the **Operations** tab, where you can create and manage the operations configured on the device.



1.8. To allow other users to use the device, navigate to the **Dependents** tab, where you can manage the profiles that have access to the device.

Note: To allow a created Administrator to use the device, the generated credentials (Administrator **ID** or **name** and creation **passphrase**) must be provided. To simplify this process, tap the share icon to export a file  or example via e-mail or WhatsApp.

1.9. If you also intend to use the device, you must create an **Administrator** profile for yourself in order to associate the device with the App using a user profile, as described in Section 2.

2. Device Usage

The device can be used by any user with valid usage profile credentials.


2.1. Profile Association with the App

Option 1 - Using Access Credentials


2.1.1. Navigate to the **Add** menu by tapping the icon  and the button .

2.1.2. Select Sign In mode.

2.1.3. Select the desired device.



2.1.4. Enter the credentials shared by the **Installer/Creator**.




Option 2 - Using a File:


2.1.1. Navigate to the **Add** menu by tapping the icon  and the button .

2.1.2. Select **Upload File** mode.

2.1.3. Select a file or submit the text provided by the **Installer/Creator**.




2.2. After the usage profile is associated, the commands preconfigured by the **Installer** will appear in the **Home** menu and will be available for use.



3. Command Addition and Management

3.1. To add or configure commands, navigate to the **Commands** menu.




4. User Profile Management

4.1. To configure your profile or your dependents, access the management menu by selecting the desired profile from the **Profile** menu.


4.2. To view information and configure your profile, navigate to the **Information** tab.

4.3. To view the operations available on the device, navigate to the **Operations** tab.



Note: To apply profile configuration changes, the **Submit** button must be pressed so that the new settings are sent to the device.

4.4. To allow other users to access the device, navigate to the **Dependents** tab, where you can manage the profiles that have access to the device.



Note: To allow a created **Dependent** to use the device, the generated credentials (profile ID or name and creation passphrase) must be provided. To simplify this process, tap the **share** icon  to export a file, for example via e-mail or WhatsApp.

For more detailed information, refer to the manuals available in the **User Guide** menu of the App.